





HURRICANE ELECTRIC  
INTERNET SERVICES

# Porting IPv4 applications to IPv4/v6 dual stack

---

Owen DeLong  
[owend@he.net](mailto:owend@he.net)

# Why is this important?



# Apologies in advance for the Text-Fest



# Summary of Porting Steps

- Sample code available at:  
[http://owend.corp.he.net/ipv6/sample\\_application/](http://owend.corp.he.net/ipv6/sample_application/)
- Change variable names when changing types.(e.g. dest\_sin -> dest6\_sin)
- Look for old variable name(s) as markers for code to be updated.
- Compile->Repair->Recompile (iterative)
- Test->Debug->Retest (iterative)



# General Changes (IPv4 to dual stack)

- AF\_INET -> AF\_INET6
- sockaddr\_in -> sockaddr\_in6,  
sockaddr\_storage (Generic storage type)
- Same structure members, similar constants,  
mostly just the address size changes.
- If necessary, check address scoping (link  
local vs. global and interface scope for link  
locals)



# Some possible gotchas not covered in the examples

- IP Addresses in logs
- IP Addresses stored in databases
- Parsing or other routines that need to deal with IP addresses (use library functions if at all possible)



# C porting example

- Refer to the Source Code Examples
- v4\_\* are IPv4 only code
- v6\_\* are same applications ported to dual stack
- By renaming affected variables, most calls that need to be updated are automatically flagged (markers).



# Migrating the server (C)

- The easy part:
  - Additional include <netinet/in.h>
  - Rename sockfd to sockfd6 (optional)
  - Change sockaddr\_in to sockaddr\_in6 (new struct) and rename as dest\_sin6 (marker)
  - update initializations of dest\_sin6 (new members)
  - change args in socket() call
  - socket related error messages (variable renaming)
  - update setsockopt(), bind(), listen()  
(variable renaming)



# Migrating the server (C)

- The easy part (cont'd):
  - ❑ update preparation for select() (variable renaming)
  - ❑ update initialization of socklen
  - ❑ update call to accept (renaming)
  - ❑ Other miscellaneous variable renaming
  - ❑ `inet_ntoa()` -> `inet_ntop()`



# Migrating the client (C)

- Similar to porting the server...
- The less easy parts
  - Need a helper function (`get_ip_str()`) to front `inet_ntop()` for different possible return structures from `getaddrinfo()`
  - replacing `gethostbyname()`/`getservbyname()` with `getaddrinfo()` requires some effort. The `getaddrinfo()` process is actually MUCH cleaner. (newer v4-only code may already use `getaddrinfo()`)
  - Remember to free memory allocated by `getaddrinfo()`



# Warning: Eye Charts ahead

- A handout with side-by side diffs of the source code is available at <http://owend.corp.he.net/ipv6/>

I  
FY  
OUCAN  
READT  
HISYO  
UREYE  
SAREBET  
TERTHANMINE

Copyright ©2009 Hurricane Electric. All Rights Reserved



# More detail on the hard parts (C)

## ■ IPv4 Only (gethostbyname):

```
/* Try as host name */
if (host_ent = gethostbyname(argv[1])) {
    dest_sin.sin_family = host_ent->h_addrtype;
    if (host_ent->h_length > sizeof( dest_sin.sin_addr)) {
        fprintf(stderr, "%s: address length wrong.\n", argv[0]);
        exit(2);
    }
    memcpy(&dest_sin.sin_addr, host_ent->h_addr_list[0], host_ent->h_length);
/* Try as IP address */
} else {
    if(dest_sin.sin_addr.s_addr = inet_addr(argv[1])) {
        fprintf(stderr, "%s: cannot find address for '%s'.\n", argv[0], argv[1]);
        exit(2);
    }
}
```



# More detail on the hard parts (C) (cont'd)

## ■ IPv4 Only (getservbyname):

```
/* Get service information */
if ((srvp = getservbyname("demo", "tcp")) == 0) {
    fprintf(stderr, "%s: cannot find port number for demo service.\n", argv[0]);
    exit(3);
} else {
    dest_sin.sin_port = srvp->s_port;
}
```



# More detail on the hard parts (C) (cont'd)

- IPv4/v6 Dual Stack (`getaddrinfo()`) does both:
  - Gets both Service and Host information at once.
  - Returns a dynamically allocated linked list
  - Don't forget to free the list when you no longer need it.

```
/* Get address info for specified host and demo service */
memset(&addrinfo, 0, sizeof(addrinfo));
addrinfo.ai_family=PF_UNSPEC;
addrinfo.ai_socktype=SOCK_STREAM;
addrinfo.ai_protocol=IPPROTO_TCP;
if (rval = getaddrinfo(argv[1], "demo", &addrinfo, &res) != 0) {
    fprintf(stderr, "%s: Failed to resolve address information.\n", argv[0]);
    exit(2);
}
```



# Trying to connect -- Differences (C)

- IPv4 Only (see example source code):

```
for(addrlist = host_ent->h_addr_list; *addrlist != NULL; addrlist++)
{
    memcpy((caddr_t)&dest.sin.sin_addr, (caddr_t)*addrlist, sizeof(dest.sin.sin_addr));
    if ((sockfd = socket(AF_INET, SOCK_STREAM, IPPROTO_TCP)) < 0)
    {
        fprintf(stderr, "%s: Could not create socket.\n", argv[0]);
        exit(4);
    }
    if (connect(sockfd, (struct sockaddr *)&dest.sin, sizeof(dest.sin)) < 0)
    {
        e_save = errno;
        (void) close(sockfd);
        errno = e_save;
        fprintf(stderr, "%s: Failed attempt to %s.\n", argv[0],
                inet_ntoa(dest.sin.sin_addr));
        perror("Socket error");
    } else {
        snprintf(s, BUFLEN, "%s: Succeeded to %s (%d).",
                 inet_ntoa(dest.sin.sin_addr), dest.sin.sin_addr);
        debug(5, argv[0], s);
        success++;
        break;
    }
}
if (success == 0)
{
    fprintf(stderr, "%s: Failed to connect to %s.\n", argv[0], argv[1]);
    exit(5);
}
```



# Trying to connect -- Differences (C)

- The new way (a bit easier) (see example code):

```
for (r=res; r; r = r->ai_next) {  
    sockfd6 = socket(r->ai_family, r->ai_socktype, r->ai_protocol);  
    if (connect(sockfd6, r->ai_addr, r->ai_addrlen) < 0)  
    {  
        e_save = errno;  
        (void) close(sockfd6);  
        errno = e_save;  
        fprintf(stderr, "%s: Failed attempt to %s.\n", argv[0],  
                get_ip_str((struct sockaddr *)r->ai_addr, buf, BUFLEN));  
        perror("Socket error");  
    } else {  
        snprintf(s, BUFLEN, "%s: Succeeded to %s.", argv[0],  
                get_ip_str((struct sockaddr *)r->ai_addr, buf, BUFLEN));  
        debug(5, argv[0], s);  
        success++;  
        break;  
    }  
}  
if (success == 0)  
{  
    fprintf(stderr, "%s: Failed to connect to %s.\n", argv[0], argv[1]);  
    freeaddrinfo(res);  
    exit(5);  
}  
printf("%s: Successfully connected to %s at %s on FD %d.\n", argv[0], argv[1],  
      get_ip_str((struct sockaddr *)r->ai_addr, buf, BUFLEN),  
      sockfd6);
```




# Migrating the client (C)

- The easy parts
  - Use the same variable name flagging method as with server.
  - Mostly update the same structure names and calls, flagged the same way.
  - `getaddrinfo()` will automatically return the AAAA and A records, so, v6/v4 is automatic with one codebase.
  - `inet_ntop()` needs a helper function (see `get_ip_str()` in the example code)



# What happens if we aren't ready?



# PERL Porting Example

- Refer to the Source Code Examples
- v4\_\* are IPv4 only code
- v6\_\* are same applications ported to dual stack
- Did not rename most variables in this example. (Small codebase, not as important)



# Server Differences (PERL)

- Add Socket6 to the modules “used” (you still need Socket, too). PERL documentation for Socket6 is minimal and examples limited.
- Gut and replace get\*byname calls (more on this next slide)
- Change protocol and address families in socket() and bind() calls.
- Minor changes to processing incoming connections (mostly related to name/address display).



# Server Differences (PERL) (cont.)

- Biggest change is conversion from `get*byname()` to `getaddrinfo()`
- Similar changes to C port (same underlying library changes)
- C `getaddrinfo()` returns linked list. PERL `getaddrinfo()` returns straight list (multiple of 5 elements, each 5 elements is a list entry).
- Gotcha on `getaddrinfo()` -- passing in `in6addr_any` does not return `in6addr_any`.



# Code Changes (PERL)

## ■ Old way (getservbyname()):

```
my $tcp = getprotobynumber('tcp');
my $tcpport = getservbyname('demo', 'tcp');
```

## ■ New way (getaddrinfo()):

```
my ($fam, $stype, $tcp, $saddr, $cname);
my @res = getaddrinfo(in6addr_any(), 'demo', AF_UNSPEC, SOCK_STREAM);
my ($tcpport, $addr);
die "$0: Could not get protocol information" unless @res;
# This is ugly, but, seems to be necessary to bind to IPv6.
$fam = 0;
($fam, $stype, $tcp, $saddr, $cname, @res) = @res while $fam != AF_INET6;
die "$0: IPv6 unsupported on this system.\n" unless ($fam == AF_INET6);
($tcpport, $addr) = unpack_sockaddr_in6($saddr);
$addr = in6addr_any();
$saddr = pack_sockaddr_in6($tcpport, $addr);
```



# Code Changes (PERL) (Cont.)

## ■ IPv4 only:

```
socket(TCPServer, PF_INET, SOCK_STREAM, $tcp) ||  
    die "$0: Could not create socket: $!";  
bind(TCPServer, sockaddr_in($tcpport, INADDR_ANY)) ||  
    die "$0: Bind failed: $!";
```

## ■ IPv4/v6 Dual Stack:

```
socket(TCPServer, PF_INET6, SOCK_STREAM, $tcp) ||  
    die "$0: Could not create socket: $!";  
bind(TCPServer, $saddr) || die "$0: Bind failed: $!";
```



# Code Changes (PERL) (Cont.)

## ■ IPv4 only:

```
my ($port, $iaddr) = sockaddr_in($paddr);
my $name = gethostbyaddr($iaddr, AF_INET);
debug(5, "TCP Connection from $name [".inet_ntoa($iaddr)."] at port $port.\n");
$CLIENTS{$CLIENT} = inet_ntoa($iaddr)."/".$port;
```

## ■ IPv4/v6 Dual Stack:

```
my ($port, $iaddr) = unpack_sockaddr_in6($paddr);
my ($name, $svc) = getnameinfo($paddr);
debug(5, "TCP Connection from $name [".inet_ntop(AF_INET6, $iaddr).
          "] at port $port.\n");
$CLIENTS{$CLIENT} = inet_ntop(AF_INET6, $iaddr)."/".$port;
```



# PERL Client Migration

- Similar changes to C client
- Add module Socket6 (just like the server)
- Rearrange the address resolution stuff for `getaddrinfo()`
- Add some handling for `AF_INET6` to the connection loop
- Convert `inet_ntoa()` to `inet_ntop()` calls.
- Handle Protocol Family for `socket()` call



# Code Changes (PERL) (Cont.)

## ■ IPv4 only:

```
my $tcp = getprotobynumber('tcp');
my $tcpport = getservbyname($port, 'tcp');
...
my ($name, $aliases, $addrtype, $length, @addrs) = gethostbyname($server);
die("$0: gethostbyname error: $!\n") if ($?);
die("Invalid server specified.\n") unless(@addrs);
socket(SOCKFD, PF_INET, SOCK_STREAM, $tcp) || die "Couldn't create socket: $!\n";
SOCKFD->autoflush(1);
```

## ■ IPv4/v6 Dual Stack:

```
my @res = getaddrinfo($server, 'demo', AF_UNSPEC, SOCK_STREAM, 'tcp');
die("Could not resolve $server or service demo: ".$res[0].".\n")
unless(scalar(@res) >= 5);
```

## ■ Note: In IPv4, socket can be recycled for multiple connects. IPv4/v6 Dual Stack, not so due to possible family change (PF\_INET/PF\_INET6)



# Code Changes (PERL) (Cont.)

## ■ IPv4 only:

```
while (@addrs)
{
    $a = shift(@addrs);
    print "Trying host ", inet_ntoa($a), ".\n";
    $dest_sin = sockaddr_in($tcpport, $a);
    last if(connect(SOCKFD, $dest_sin));
    print "Failed to connect to ", inet_ntoa($a), ".\n";
    $dest_sin = -1;
}
```



# Code Changes (PERL) (Cont.)

## ■ IPv4/v6 Dual Stack:




```
my ($fam, $stype, $proto, $saddr, $cname);
my ($port, $addr);
while (scalar(@res) >= 5)
{
    ($fam, $stype, $proto, $saddr, $cname, @res) = @res;
    next unless($saddr);
    $cname = $server unless $cname;
    print "Unpacking $cname...";
    ($port, $addr) = ($fam == AF_INET6) ?
        unpack_sockaddr_in6($saddr) : sockaddr_in($saddr);
    $addr = inet_ntop($fam, $addr);
    print "Trying host $cname ($addr) port $port.\n";
    my $PF = ($fam == AF_INET6) ? PF_INET6 : PF_INET;
    socket(SOCKFD, $PF, SOCK_STREAM, $proto) || die "Couldn't create socket: $!\n";
    SOCKFD->autoflush(1);
    last if(connect(SOCKFD, $saddr));
    close SOCKFD;
    print "Failed to connect to $cname ($addr): $!. \n";
    $saddr = -1;
}
```

## ■ This isn't as bad as it looks. Need better libraries?



# No, really, what happens?

Communication between IPv4 nodes and IPv6 nodes



# Python Porting Example

- Refer to the Source Code Examples
- v4\_\* are IPv4 only code
- v6\_\* are same applications ported to dual stack
- Did not rename most variables in this example. (Small codebase, not as important)



# Server Differences (Python)

- Gut and replace get\*byname() calls (more on this next slide)
- Replace default fatal error for single attempt at binding with iterative loop to handle multiple address families
- Minor changes to processing incoming connections (4-tuple instead of 2).



# Code Changes (Python)

## ■ Old way (`getservbyname()`):

```
tcp = socket.getprotobynumber('tcp')
tcpport = socket.getservbyname(port, 'tcp')
```

## ■ New way (`getaddrinfo()`):

```
try:
    res = socket.getaddrinfo(None, "demo", socket.AF_UNSPEC, \
        socket.SOCK_STREAM, 0, socket.AI_PASSIVE)
except socket.gaierror, (errno, msg):
    print >> sys.stderr, "%s: failed with error %s." \
        % (prog, msg)
    sys.exit(1)
```



# Listening (Python)

## ■ Old way:

```
s = socket.socket(socket.AF_INET, socket.SOCK_STREAM)
s.setblocking(0)
s.setsockopt(socket.SOL_SOCKET, socket.SO_REUSEADDR, 1)
s.bind('', tcpport)
s.listen(socket.SOMAXCONN)
```

## ■ New way:

```
for (fam, stype, proto, cname, saddr) in res:
    if (fam is not socket.AF_INET6): continue
    (addr, tcpport, flow, scope) = saddr
    try:
        s = socket.socket(fam, stype, proto)
    except socket.error, (errno, msg):
        s = None
        continue
    try:
        s.setblocking(0)
        s.setsockopt(socket.SOL_SOCKET, socket.SO_REUSEADDR, 1)
        s.bind('', tcpport)
        s.listen(socket.SOMAXCONN)
    except socket.error, (errno, msg):
        s.close()
        s = None
        continue
    break
```



# Code Changes (Python) (Cont.)

- Old way:

```
(host, port) = addr
```

- New way:

```
(host, port, flow, scope) = addr
```

- Clarification: this is parsing the output from the accept() call which returns (conn, addr). As you can see, the IPv6 compatible change is the additional elements in the returned “addr” tuple.
- Used to make the address presentable in debugging output and user messages.



# Python Client Migration

- Similar changes to C client
- Rearrange the address resolution stuff for `getaddrinfo()`
- Add some handling for `AF_INET6` to the connection loop
- Convert `inet_ntoa()` to `inet_ntop()` calls.
- Handle Protocol Family for `socket()` call



# Code Changes (Python)

## ■ Old Way:

```
for i in addrlist:  
    print "Trying host %s." % i  
    try:  
        s.connect((i,tcpport))  
    except socket.error, (errno, msg):  
        print "Failed to connect to %s: %s." % (i, msg)  
        continue  
    break  
else:  
    print >>sys.stderr, "Connect failed."  
    sys.exit(1)
```



# Code Changes (Python) (Cont.)

## ■ New Way:

```
for (fam, stype, proto, cname, saddr) in res:
    if (fam is socket.AF_INET6):
        (host, port, flow, scope) = saddr
    elif (fam is socket.AF_INET):
        (host, port) = saddr
    else:
        debug(3, "Skipping unknown address family:", fam)
        continue
    print "Trying host %s (%s) port %d." % (cname, host, port)
    try:
        s = socket.socket(fam, stype, proto)
    except socket.error, (errno, msg):
        s = None
        continue
    try:
        s.connect(saddr)
    except socket.error, (errno, msg):
        s.close()
        s=None
        print "Failed to connect to %s (%s): %s." % (cname, host, msg)
        continue
    if s: break
if s is None:
    print >> sys.stderr, "%s: No successful connection." % prog
    sys.exit(1)
```



# Connecting (Python) (Cont.)

- In addition, there are minor modifications required in the successful connection message (variable names in print arguments).
- No other code changes needed in Python.



# Function Replacement Guide (all languages)

Old Function	Current Function
get*by*()	getaddrinfo(), getnameinfo()
socket()	socket()†
bind()	bind()†
listen()	listen()
connect()	connect()†
recv*()	recv*()†
send*()	send*()†
accept()	accept()
read()/write()	read()/write()
inet_ntoa()/inet_aton()	inet_ntop()/net_pton() or getnameinfo()†
† parameters change for IPv6 support	



# Structure Replacement Guide

Old Structure	Current Structure
sockaddr_in, sockaddr_storage† in_addr, int (Don't do this, even in v4 only)	sockaddr_in6, sockaddr_storage†
hostent	
servent	addrinfo
†sockaddr_storage is a pointer type only can point to either actual type.	



# Q&A



Copy of slides available at:  
<http://owend.corp.he.net/ipv6/PortMeth.pdf>

## Contact:

Owen DeLong  
IPv6 Evangelist  
Hurricane Electric  
760 Mission Court  
Fremont, CA 94539, USA  
<http://he.net/>

owend at he dot net  
+1 (408) 890 7992

